Accessing Entire Operations Master Resources

This subsection covers the following topics:

- Handling Entire Operations Master Resources
- Description of the Function Codes

Handling Entire Operations Master Resources

You can handle master resources with the following statement:

```
CALLNAT 'NOPURS1N'
    P-FUNCTION P-RC P-NODE P-RESOURCE P-TYPE P-INIT-QTY P-USED-QTY
```

Meaning of the parameters:

Parameter	Format	Usage		
P-FUNCTION	A01	in	Function code:	
			A	Add a resource.
			D	Delete a resource.
			M	Modify a resource.
			T	Test a resource.
P-RC	N03	out	Return code:	
			0	Function ok; resource found.
			1	Resource not found.
			2	Resource already exists.
			3	Inconsistent values.
			4	Initial quantity may not be modified.
			101	Invalid function code.
			102	Resource name missing.
P-NODE	N03	in	Not used; use constant with value=0.	
P-RESOURCE	A20	in	Name of the resource.	
P-TYPE	A01	in	Type of resource (only for FUNCTION = ‡AŸ)	
			N	Not quantitative.
			R	Quantitative, re-usable.
			U	Quantitative, not re-usable.
P-INIT-QTY	P7.2	in/out	Total quantity.	
P-USED-QTY	P7.2	in/out	Currently used quantity.	

Description of the Function Codes

Meaning of the function codes:

Code	Description
A	Adds a new resource definition. You must give values for P-TYPE, P-INIT-QTY and P-QTY.
D	Deletes a resource definition.
M	Used to modify the values P-INIT-QTY.
T	Returns the current values of P-INIT-QTY and P-QTY.

Note:

- Before using **M** for modifications, you should use **T** to read the present values (unless you want to enter an absolute value).
- The currently used amount of a resource can no longer be modified directly. You must perform a resource allocation or deallocation with the API NOPURE1N to modify the currently used resource amount.